

T2 4K Software Update Instruction


This document instructs how to update the T2 4K software to the latest version using downloaded files.

IMPORTANT NOTIFICATION

This update only for T2 4K series, cannot be applied to other T2 series.

Preparation

- 1) Right-click on T2 update .zip file then choose [Properties]
- 2) Go to [Genera]. Confirm if 'Unblock' option exists, if yes, untick the option and click [Apply] then [OK] button.



- 3) Create "T2_Upd" folder then unzip the .zip file.
- 4) Copy "T2_Upd" folder into an USB stick.
- 5) Connect both keyboard and mouse to the T2.

Start T2 in maintenance mode

- 1) Start T2 in maintenance mode.
- 2) Touch or click password entry field and enter 'admin' as the password, and then click [OK] button.
- 3) Confirmation message will appear. Click [Yes] button.
- 4) T2 will restart in maintenance mode and the maintenance tool will start automatically.



Update T2 software

- 1) Choose [Start] > [My Computer] and open "T2_Upd" folder in the USB storage device.
- 2) Double-click "T2_4K_Updater.exe". Software will be updated automatically.
- 3) If below screen appears, click [Install] button.



- 4) Click [Yes] button in restart required dialog box to launch file update. T2 will restart in maintenance mode.
 - **NOTE:** If you click [No] button, you need to restart in maintenance mode manually before starting the T2 in Command Center mode. If the step is skipped, the T2 may not work properly.
- 5) Restart the T2 in Command center mode.